

GET RAW WORKING WITH YOUR CAMERA

This guide is designed to get RAWs from your camera working with your version of Photoshop...

EVERY NEW CAMERA MODEL that hits the shelves has a unique type of RAW format, and that means you'll almost certainly need to upgrade or at least update your RAW conversion software if you invest in a new camera. There are different proprietary RAW formats from each maker, such as NEF from Nikon, CR2 from Canon, PEF from Pentax, ORF from Olympus, RAF from Fuji, ARW from Sony, and so on, but the thing to remember is that a

NEF from a Nikon D200 camera, for example, is completely different to a NEF from a D300, and a CR2 from a Canon 450D is nothing like the CR2 from a 550D. It doesn't matter if the file extension is the same - what's important is that your camera model is supported by your RAW software, and that's down to how recent the software is compared to your camera.

If your software is older than the camera you're shooting with, then it won't work until


you upgrade or update it. This compatibility problem accounts for about 90 percent of the RAW questions we receive, and though it seems confusing at first, it's easy to swallow if you simply remember that every camera has its own bespoke RAW format, and if your camera was invented *after* you got your RAW software, then the software is simply too old to work!

Making Photoshop or Elements compatible with your camera's RAWs means downloading the latest update for Adobe Camera Raw. Unless you have the latest version of Photoshop or Elements, though, this may also mean upgrading the software, too, as the more recent updates won't work with the older versions. Our flow chart explains it all...

GET YOUR RAWS WORKING NOW!




START HERE



STEP 1 RAW file won't open in Photoshop

If the Bridge or Organizer can't display your RAW files, or you try to open a RAW directly and Photoshop gives you a warning telling you it doesn't recognise the file, then you need to update Camera Raw.



STEP 2 Update Adobe Camera Raw

Go to www.adobe.com/uk and head to the **Downloads** section. You'll find the latest versions of Camera Raw here. This will work with all compatible cameras, but you will need the very latest version of Photoshop or Elements to run it.

[FIND OUT HOW TO UPDATE BELOW](#)

IF YOU DON'T HAVE THE LATEST VERSION GO TO STEP 3

STEP 3 Older version of Photoshop or Elements

If you don't have the latest version, then provided your camera isn't very recent, you may still be able to use a Camera Raw update. Check the following pages of this guide to see what version of Camera Raw is required for your camera, and what version of Photoshop you need to run it. Once you know this, type the version (eg. *Camera Raw 3.7*) into the **Search** bar at www.adobe.com and download & install the update. You'll find instructions included on how to install it with your version.

IF YOU CAN'T UPDATE...

Use the [DNG CONVERTER](#) or [UPGRADE PHOTOSHOP](#)

HOW TO

Upgrade Photoshop

If you have a fully licensed package, pay a visit to www.adobe.com/uk and you can upgrade to the latest Photoshop CS5 from CS2, CS3 or CS4 for £190, or from Elements 6, 7 or 8 for £560.

If you want to upgrade to Elements 9, from an older version, it'll set you back £64, but if you shop around at other retail websites you can often find it even cheaper than that.



HOW TO

Update to the latest version of Camera Raw

If you're using the latest versions of Photoshop or Elements, first go to the **Help** menu and pick **Updates** for an automatic installation. If this is unavailable in your version, go to www.adobe.com/uk and click on the **Downloads** menu. Find the update you need, using our Compatibility Guide as an aid, and download it. Once you've done this you may need to unzip the file (just double-click on it to achieve this) and manually install it (see below).

GET YOUR CAMERA RAW SORTED NOW

TO INSTALL MANUALLY WITH ADOBE PHOTOSHOP ELEMENTS

- Close Photoshop Elements.
- Double-click **Computer**.
- Double-click **Local Disk (C:)**
- Navigate to: **Program Files\Common Files\Adobe\Plug-Ins\Elements (version)\File Formats** and leave this window open on screen.
- Drag the existing *Camera Raw.8bi* plug-in to another location (such as a new folder on your desktop). Ensure you keep this in case you have any problems and need to change back.
- Drag the new *Camera Raw.8bi* plug-in from the (unzipped) download into the folder mentioned above - the window should still be open.
- Launch Photoshop Elements.

TO INSTALL MANUALLY WITH ADOBE PHOTOSHOP


- Close Photoshop and Bridge.
- Double-click **Computer**.
- Double-click **Local Disk (C:)**
- Navigate to: **Program Files\Common Files\Adobe\Plug-Ins\CS (version)\File Formats**, and leave this window open.
- Move the existing *Camera Raw.8bi* plug-in to another location (such as a new folder on your desktop). Ensure you keep this in case you have any problems and need to change back.
- Drag the new *Camera Raw.8bi* plug-in from the (unzipped) download into the folder mentioned above.
- Launch Photoshop or Adobe Bridge, and the job is done.

HOW TO

Install & use the Adobe DNG converter




If your camera's too new for your software and no Camera Raw update is possible, then there is a workaround if you don't want to splash out on a software upgrade. The *Adobe DNG converter* will take files from any compatible camera and turn them into DNG format. These will then open in just about any RAW converter - including the early ones found in Photoshop CS and CS2.




1 START DOWNLOAD UPDATE.

Go to www.adobe.com/uk and click **Downloads** at the top of the screen. On the right-hand side locate the latest *DNG Converter X.X update* and click on the link for your system (*Windows* or *Mac*).



2 EXTRACT THE FILE.

Download the file and choose a location to save it to. Once saved, double-click the file to open it in an extraction program like *WinZip*. Now click on the *Adobe DNG Converter*, click the 'extract' icon and select your Desktop.



3 FINAL STEP CONVERT RAWS.

Adobe's DNG converter is now on your desktop. Launch it and all you need to do is select the location of the RAWs to be converted, a destination to save them to, and select a naming convention. Hit **Convert** and it's done!

CAMERA RAW COMPATIBILITY

Find your camera then read across for the version of Camera Raw you need...

Camera	Camera Raw Version	Photoshop Version	Elements Version
CANON			
Canon EOS-1D	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS-1D Mark II	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS-1D Mark II N	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS-1D Mark III	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon EOS-1D Mark IV	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Canon EOS-1Ds	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS-1Ds Mark II	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS-1Ds Mark III	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon EOS 10D	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS 1000D	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon EOS 1100D	v6.4	CS5	9 or 10
Canon EOS 20D	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS 20Da	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS 30D	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS 300D	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS 350D	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS 40D	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon EOS 400D	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS 450D	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon EOS 5D	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Canon EOS 5D Mark II	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Canon EOS 50D	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon EOS 500D	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Canon EOS 550D	v5.7	CS4 or CS5	8, 9 or 10
Canon EOS 60D	v6.2	CS5	8, 9 or 10
Canon EOS 600D	v6.4	CS5	9, 9 or 10
Canon EOS 7D	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Canon EOS D30	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon EOS D60	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot 600	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot A5	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot A50	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot G1	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot G2	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot G3	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot G5	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot G6	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot G9	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Canon PowerShot G10	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Canon PowerShot G11	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Canon PowerShot G12	v6.3	CS5	8, 9 or 10
Canon PowerShot Pro 1	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot Pro70	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot Pro90 IS	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S30	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S40	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S45	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S50	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S60	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S70	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Canon PowerShot S90	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Canon PowerShot S95	v6.3	CS5	8, 9 or 10
Canon PowerShot SX1 IS	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
CASIO			
Casio EXILIM EX-F1	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Casio EXILIM EX-FH100	v6.2	CS5	8, 9 or 10
Casio EXILIM EX-FH20	v5.3	CS4 or CS5	6, 7, 8, 9 or 10

* Apple Mac users note ACR plug-in 3.7 & 4.6 will work on an earlier version of Photoshop Elements, i.e. Elements 3 for v3.7 and 4 for v4.6

Camera	Camera Raw Version	Photoshop Version	Elements Version
CONTAX			
Contax N Digital	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
EPSON			
Epson R-D1	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Epson R-D1s	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Epson R-D1x	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Epson Valeo 22	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
FUJIFILM			
Fujifilm FinePix E900	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix F550 EXR	v6.4	CS5	9 or 10
Fujifilm FinePix F600 EXR	v6.5	CS5	9 or 10
Fujifilm FinePix F700	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Fujifilm FinePix HS10	v6.2	CS5	8, 9 or 10
Fujifilm FinePix HS20 EXR	v6.4	CS5	9 or 10
Fujifilm FinePix IS Pro	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Fujifilm FinePix IS-1	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Fujifilm Finepix S100fs	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S2 Pro	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S20 Pro	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S200 EXR	v6.4	CS5	9 or 10
Fujifilm FinePix S3 Pro	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S5 Pro	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S5000 Z	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Fujifilm FinePix S5200/S600	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S6000fd/S6500fd	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S7000 Z	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Fujifilm FinePix S9000/9500	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix S9100/9600	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Fujifilm FinePix X100	v6.4	CS5	9 or 10
HASSELBLAD			
Hasselblad 503CWD	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CF-22	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CF-22MS	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CF-39	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CF-39MS	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CFH-22	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CFH-39	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad CFV	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H2D	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Hasselblad H2D-22	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H2D-39	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3D-22	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3D-31	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3D-39	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3DII-22	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3DII-31	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3DII-39	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3DII-39MS	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H3DII-50	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Hasselblad H4D-40	v6.4	CS5	9 or 10
Hasselblad H4D-60	v6.5	CS5	9 or 10
KODAK			
Kodak DCS 14n	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Kodak DCS Pro 14nx	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Kodak DCS Pro SLR/n	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Kodak DCS720x	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Kodak DCS760	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Kodak EasyShare P712	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Kodak EasyShare P850	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Kodak EasyShare P880	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Kodak EasyShare Z1015 IS	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Kodak EasyShare Z980	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Kodak EasyShare Z990	v6.4	CS5	9 or 10

* Apple Mac users note ACR plug-in 3.7 & 4.6 will work on an earlier version of Photoshop Elements, i.e. Elements 3 for v3.7 and 4 for v4.6

CAMERA RAW COMPATIBILITY

Camera	Camera Raw Version	Photoshop Version	Elements Version
KONICA MINOLTA			
Konica Minolta DiIMAGE 5	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta DiIMAGE 7	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta DiIMAGE 7Hi	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta DiIMAGE 7i	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta DiIMAGE A1	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta DiIMAGE A2	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta DiIMAGE A200	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Konica Minolta Dynax 5D/Maxxum 5D	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Konica Minolta Dynax 7D/Maxxum 7D	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Kodak Z981	v5.7	CS4 or CS5	8, 9 or 10
LEAF			
Leaf AFill 6	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf AFill 7	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf Aptus 17	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf Aptus 22	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leaf Aptus 54s	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf Aptus 65	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leaf Aptus 65s	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Leaf Aptus 75	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leaf Aptus 75s	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf Aptus II 5	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Leaf Aptus II 6	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf Aptus II 7	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Leaf Aptus II 8	v5.7	CS4 or CS5	8, 9 or 10
Leaf Aptus II 10R	v5.7	CS4 or CS5	8, 9 or 10
Leaf Aptus II 12	v6.5	CS5	9 or 10
Leaf Aptus II 12R	v6.5	CS5	9 or 10
Leaf Valeo 11	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Leaf Valeo 17	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leaf Valeo 22	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Leaf Valeo 6	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
LEICA			
Leica Digilux 2	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10*
Leica Digilux 3	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leica Digital-Modul-R	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Leica D-Lux 2	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leica D-Lux 3	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Leica D-Lux 4	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Leica M8	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Leica S2	v6.2	CS5	8, 9 or 10
Leica V-LUX1	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
MAMIYA			
Mamiya DM22	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya DM28	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya DM33	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya DM40	v5.7	CS4 or CS5	8, 9 or 10
Mamiya DM56	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya M18	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya M22	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya M31	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Mamiya ZD	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
NIKON			
Nikon Coolpix 5000	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Nikon Coolpix 5400	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Nikon Coolpix 5700	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Nikon Coolpix 8400	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon Coolpix 8700	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10*
Nikon Coolpix 8800	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon Coolpix P6000	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Nikon Coolpix P7000	v6.3	CS5	8, 9 or 10
Nikon Coolpix P7100	v6.5	CS5	9 or 10

* Apple Mac users note, ACR plug-in 3.7 & 4.6 will work on an earlier version of Photoshop Elements, i.e. Elements 3 for v3.7 and 4 for v4.6

Camera	Camera Raw Version	Photoshop Version	Elements Version
Nikon D1/D1H/D1X	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Nikon D100	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Nikon D2H	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Nikon D2Hs	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D2X	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D2Xs	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D200	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D3	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Nikon D3s	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10*
Nikon D3X	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Nikon D300	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Nikon D300s	v5.5	CS4 or CS5	6, 7, 8, 9 or 10
Nikon D3000	v5.5	CS4 or CS5	6, 7, 8, 9 or 10
Nikon D3100	v6.3	CS5	8, 9 or 10
Nikon D40	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D40x	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Nikon D50	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D5000	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Nikon D5100	v6.4	CS5	9 or 10
Nikon D60	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Nikon D70	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D70s	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D700	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Nikon D7000	v6.3	CS5	8, 9 or 10
Nikon D80	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Nikon D90	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
OLYMPUS			
Olympus C-5050 Zoom	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Olympus C-5060 Zoom	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Olympus C-7070 Wide Zoom	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus C-8080 Wide Zoom	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Olympus E-1	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Olympus E-10	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Olympus E-20	v2.4	CS, CS2, CS3, CS4 or CS5	3, 4, 5, 6, 7, 8, 9 or 10
Olympus E-3	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus E-30	v5.3	CS4 or CS5	6, 7, 8, 9 or 10
Olympus E-300	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus E-330	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus E-400	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus E-410	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus E-420	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus E-450	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Olympus E-5	v6.3	CS5	8, 9 or 10
Olympus E-500	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus E-510	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus E-520	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus E-600	v6.1	CS5	8, 9 or 10
Olympus E-620	v5.4	CS4 or CS5	6, 7, 8, 9 or 10
Olympus E-P1	v5.5	CS4 or CS5	6, 7, 8, 9 or 10
Olympus E-P2	v5.6	CS4 or CS5	6 (Mac), 7, 8, 9 or 10
Olympus E-P3	v6.5	CS5	9 or 10
Olympus E-PL1	v5.7	CS4 or CS5	8, 9 or 10
Olympus E-PL1s	v6.4	CS5	9 or 10
Olympus E-PL2	v6.4	CS5	9 or 10
Olympus E-PL3	v6.5	CS5	9 or 10
Olympus E-PM1	v6.5	CS5	9 or 10
Olympus SP-310	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus SP-320	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus SP-350	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus SP-500 UZ	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus SP-510 UZ	v3.7	CS2, CS3, CS4 or CS5	4, 5, 6, 7, 8, 9 or 10*
Olympus SP-550 UZ	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus SP-560 UZ	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus SP-565 UZ	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus SP-570 UZ	v4.6	CS3, CS4 or CS5	5, 6, 7, 8, 9 or 10*
Olympus XZ-1	v6.4	CS5	9 or 10
PANASONIC			
Panasonic DMC-FX150	v5.3	CS4 or CS5	6, 7, 8, 9 or 10

* Apple Mac users note, ACR plug-in 3.7 & 4.6 will work on an earlier version of Photoshop Elements, i.e. Elements 3 for v3.7 and 4 for v4.6



CAMERA RAW COMPATIBILITY

Camera	Camera Raw Version	Photoshop Version	Elements Version
Panasonic DMC-FZ100	v6.2	CS5	8,9or10
Panasonic DMC-FZ150	v6.5	CS5	9or10
Panasonic DMC-FZ18	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Panasonic DMC-FZ28	v5.3	CS4 or CS5	6,7,8,9or10
Panasonic DMC-FZ30	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Panasonic DMC-FZ35	v5.5	CS4 or CS5	6,7,8,9or10
Panasonic DMC-FZ38	v5.6	CS4 or CS5	6 (Mac), 7,8,9or10
Panasonic DMC-FZ40 (FZ45)	v6.2	CS5	8,9or10
Panasonic DMC-FZ50	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Panasonic DMC-FZ8	v4.6	CS3 or CS4	5,6,7,8,9or10*
Panasonic DMC-G1	v5.3	CS4 or CS5	6,7,8,9or10
Panasonic DMC-G10	v5.7	CS4 or CS5	8,9or10
Panasonic DMC-G2	v5.7	CS4 or CS5	8,9or10
Panasonic DMC-G3	v6.5	CS5	9or10
Panasonic DMC-GF1	v5.5	CS4 or CS5	6,7,8,9or10
Panasonic DMC-GF2	v6.3	CS5	8,9or10
Panasonic DMC-GF3	v6.5	CS5	9or10
Panasonic DMC-GH1	v5.4	CS4 or CS5	6,7,8,9or10
Panasonic DMC-GH2	v6.3	CS5	8,9or10
Panasonic DMC-L1	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Panasonic DMC-L10	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Panasonic DMC-LC1	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Panasonic DMC-LX1	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Panasonic DMC-LX2	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Panasonic DMC-LX3	v5.3	CS4 or CS5	6,7,8,9or10
Panasonic DMC-LX5	v6.2	CS5	8,9or10
PENTAX			
Pentax *ist D	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Pentax *ist DL	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Pentax *ist DL2	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Pentax *ist DS	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Pentax *ist DS2	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Pentax K100D	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Pentax K100D Super	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Pentax K10D	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Pentax K110D	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Pentax K20D	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Pentax K-5	v6.3	CS5	8,9or10
Pentax K-7 (PEF)	v5.4	CS4 or CS5	6,7,8,9or10
Pentax K-m	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Pentax K-r	v6.3	CS5	8,9or10
Pentax K-x	v5.6	CS4 or CS5	6 (Mac), 7,8,9or10
Pentax 645D	v6.2	CS5	8,9or10
Pentax Q	v6.5	CS5	9or10
PHASE ONE			
Phase One H20	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One H25	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One IQ140	v6.5	CS5	9or10
Phase One IQ160	v6.5	CS5	9or10
Phase One IQ180	v6.5	CS5	9or10
Phase One P20	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P20+	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P21	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P21+	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P25	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P25+	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P30	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P30+	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P40+	v6.5	CS5	9or10
Phase One P45	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Phase One P45+	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*

* Apple Mac users note, ACR plug-in 3.7 & 4.6 will work on an earlier version of Photoshop Elements, i.e. Elements 3 for v3.7 and 4 for v4.6

Camera	Camera Raw Version	Photoshop Version	Elements Version
Phase One P65+	v6.5	CS5	9or10
RICOH			
Ricoh GR Digital	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Ricoh GR Digital II	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Ricoh GX100	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Ricoh GX200	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Ricoh GXR, GR LENS A12 28mm F2.5	v6.3	CS5	8,9or10
Ricoh GXR MOUNT A12	v6.5	CS5	9or10
SAMSUNG			
Samsung GX-10	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Samsung GX-1L	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Samsung GX-1S	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Samsung Pro 815	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Samsung NX10	v6.2	CS5	8,9or10
Samsung NX11	v6.4	CS5	9or10
Samsung NX100	v6.3	CS5	8,9or10
Samsung TL350 (WB2000)	v6.3	CS5	8,9or10
Samsung TL500 (EX1)	v6.2	CS5	8,9or10
SIGMA			
Sigma DP1	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Sigma DP1s	v5.6	CS4 or CS5	6 (Mac), 7,8,9or10
Sigma DP2	v5.4	CS4 or CS5	6,7,8,9or10
Sigma SD10	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
Sigma SD14	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Sigma SD9	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8,9or10
SONY			
Sony A100	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Sony A290	v6.2	CS5	8,9or10
Sony A200	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Sony A230	v5.4	CS4, CS4 or CS5	6,7,8,9or10
Sony A300	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Sony A330	v5.4	CS4, CS4 or CS5	6,7,8,9or10
Sony A350	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Sony A380	v5.4	CS4 or CS5	6,7,8,9or10
Sony A390	v6.2	CS5	8,9or10
Sony A450	v5.7	CS4 or CS5	8,9or10
Sony A500	v5.6	CS4 or CS5	6 (Mac), 7,8,9or10
Sony A550	v5.6	CS4 or CS5	6 (Mac), 7,8,9or10
Sony A560	v6.3	CS5	8,9or10
Sony A580	v6.3	CS5	8,9or10
Sony A700	v4.6	CS3, CS4 or CS5	5,6,7,8,9or10*
Sony A850	v5.6	CS4 or CS5	6 (Mac), 7,8,9or10
Sony A900	v4.6	CS3, CS4 or CS5	5,6,7,8or9*
Sony DSC-F828	v2.4	CS, CS2, CS3, CS4 or CS5	3,4,5,6,7,8or9
Sony DSC-R1	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Sony DSC-V3	v3.7	CS2, CS3, CS4 or CS5	4,5,6,7,8,9or10*
Sony NEX-3	v6.2	CS5	8,9or10
Sony NEX-C3	v6.5	CS5	9or10
Sony NEX-5	v6.2	CS5	8,9or10
Sony NEX-5N	v6.5	CS5	9or10
Sony SLT-A33	v6.2	CS5	8,9or10
Sony SLT-A35	v6.5	CS5	9or10
Sony SLT-A55V	v6.2	CS5	8,9or10
Sony SLT-A65	v6.5	CS5	9or10
Sony SLT-A77	v6.5	CS5	9or10



ORDER A SUBSCRIPTION OR BACK ISSUE! 01858 436 866



Missed out on a technique or feature? Then order a back issue of the magazine you need for £6.50 (including UK P&P) simply by calling the number above. And to make sure you never miss an issue again, why not take out a subscription?